



How to “Burn” CDs using Roxio Easy CD Creator


- Insert blank CDR
- Start **Easy CD Creator** to choose “Make a **Data CD**”.
 - o In most cases, this application will automatically open when CDR is inserted



The above picture describes the C:\Apps directory to be burned to CD

- Highlight folder(s) or files you would like to copy
- Then click on Add (middle of window ..has light blue arrow) (Drag ‘n drop works as well)
- You’ll then see the Apps folder appear on lower right window
- Also notice the Size this will take on CD at the very bottom
- (44.4MB out of 658.7MB available on CD) Yes, that means you can fit 658MB on a CD!
- Click Record

Record CD Setup

 **Select CD-R Drive:** E: _NEC NR-7900A

Write Speed: 24x MAX

Number of Copies: 1

☐ Copy to hard drive first.
☐ Write CD-Text.
☒ Buffer underrun prevention

Start Recording
Cancel
Help


Information
 The selected Record Method finalizes the session. The CD itself is not finalized so additional sessions can be added later.


Hide Options

Record Options
☒ Record CD
☐ Test Only
☐ Test and Record CD

Set as Default


Record Method


 ☒ **Track-At-Once**
☐ Don't Finalize Session
☒ Finalize Session. Don't Finalize CD
☐ Finalize CD

 ☐ **Disc-At-Once**
☐ Allow another recording

Click “Start Recording”

Record CD Progress

 **Finished!**

 **Copy 1 of 1**

Progress
 100%
 Remaining Time: 0:00 minutes

Disc Progress
 CD created successfully.
 100%
 Remaining Time: 0:00 minutes

Selected Write Speed: 24x MAX
 Actual Write Speed: 16x

OK **Cancel** << **Hide Details**

Recording to Drive: E
 Format: Data CD
 Method: Track at Once
 Buffer Level:
 Block:
 Bytes Remaining:

	Total	Written	Skipped
Tracks	1	1	--
Files	200	200	--

This screen shows job has “Finished!” your done.
 Label CD with soft marker.